



Katalógusok importálásának menete a Tekla Structures program esetén.


1. A katalógusokban szereplő keresztmetszetek használatához ki kell választani a Tekla Structures menüjében a „Catalogs”, majd a „Profile catalog” opciókat.



2. A megjelenő ablakban a már, az eddigi használat során betöltött profilok jelennek meg. Amennyiben még nem töltöttünk be profilokat, abban az esetben a bal oldali rubrika üres.



3. A következő lépés, hogy az elkészített Z, C, U és Kalap profiljainkat betöltsük. Ezt az alsó sávban látható „Import”, vagy az „Import directory” opciókkal tehetjük meg. Az előugró ablakban kiválaszthatjuk a katalógusaink helyét, ahonnan be szeretnénk tölteni azokat. A katalógusok kiterjesztése a „lis”. A felugró ablakban megjelenik az összes profil, ami a katalógusokban szerepel. Kijelöléssel választhatjuk ki, hogy melyiket akarjuk beimportálni (ha az összeset, akkor az összeset kiválasztjuk). Jobb oldalon levő opciókkal eldönthetjük, hogy a már esetleg létező, azonos tulajdonságú profilokat felülírjuk az újakkal (Replace), vagy beolvastjuk az újakat a létezők közé (Merge).



The screenshot shows a dialog box titled "Review import items" with a close button (X) in the top right corner. The dialog contains a table with four columns: "Type", "Name", "Status", and "Action". The table lists 32 profile entries, all with a status of "New" and an action of "Unknown". The profiles are listed in a grid-like format, with names such as "LINDAB - HAT", "LINDAB-C/100/1.0", "LINDAB-C/100/1.2", etc., up to "LINDAB-C/220E...". To the right of the table, there are four buttons: "Leave", "Merge", "Replace", and "Continue".

Type	Name	Status	Action
Profile	LINDAB - HAT	New	Unknown
Profile	LINDAB-C/100/1.0	New	Unknown
Profile	LINDAB-C/100/1.2	New	Unknown
Profile	LINDAB-C/100/1.5	New	Unknown
Profile	LINDAB-C/100/2.0	New	Unknown
Profile	LINDAB-C/120/1.0	New	Unknown
Profile	LINDAB-C/120/1.2	New	Unknown
Profile	LINDAB-C/120/1.5	New	Unknown
Profile	LINDAB-C/120/2.0	New	Unknown
Profile	LINDAB-C/120/2.5	New	Unknown
Profile	LINDAB-C/150/1.0	New	Unknown
Profile	LINDAB-C/150/1.2	New	Unknown
Profile	LINDAB-C/150/1.5	New	Unknown
Profile	LINDAB-C/150/2.0	New	Unknown
Profile	LINDAB-C/150/2.5	New	Unknown
Profile	LINDAB-C/180/1.2	New	Unknown
Profile	LINDAB-C/180/1.5	New	Unknown
Profile	LINDAB-C/180/2.0	New	Unknown
Profile	LINDAB-C/180/2.5	New	Unknown
Profile	LINDAB-C/200/1.0	New	Unknown
Profile	LINDAB-C/200/1.2	New	Unknown
Profile	LINDAB-C/200/1.5	New	Unknown
Profile	LINDAB-C/200/2.0	New	Unknown
Profile	LINDAB-C/200/2.5	New	Unknown
Profile	LINDAB-C/200E...	New	Unknown
Profile	LINDAB-C/200E...	New	Unknown
Profile	LINDAB-C/200E...	New	Unknown
Profile	LINDAB-C/200E...	New	Unknown
Profile	LINDAB-C/220/1.5	New	Unknown
Profile	LINDAB-C/220/2.0	New	Unknown
Profile	LINDAB-C/220/2.5	New	Unknown
Profile	LINDAB-C/220/3.0	New	Unknown
Profile	LINDAB-C/220E...	New	Unknown
Profile	LINDAB-C/220E...	New	Unknown
Profile	LINDAB-C/220E...	New	Unknown

4. A C és Z profilok a „Cold rolled profiles” alá lesznek beosztva, ahogy a képen is látható, az U profilok a „U profiles” alá, valamint a kalap profil a „Hat profiles” alá.

