



# Lindab Pascal system management

## Application loader guide

Regula Master HTML 3.1  
Regula Combi version 1.5




# Application loader guide

## Application loader guide

### Up-/downgrade Regula Master.

1. Download and install Application Loader from lindQST.com (Pascal system manager / Regula Master HTML – related documents).
2. Connect your router to PC and to Regula Master.
3. Regula Master will get an IP-address, which is visible in the top main display menu by pressing right arrow. If you connect to an internal network (with DHCP) you don't need any extra router you just connect to the network (via Wi-Fi or cable).


### Get connected



# Application loader guide


4.

Click left mouse button on Corriqo E or Lindab.



5.


Click left mouse button on latest version (or desired), then click Communication, a new window will appear.



# Application loader guide


6.

Click on Use a TCP/IP port in this controller, a new window will appear.



7.

Click on the Regula Master you want to update and then press ok.



# Application loader guide

8.

Communication Settings

Use a Serial communication in this controller

Serial Number:  Search...

Communication Tool...

Use a TCP/IP port in this controller

Current Name:  Search...

Serial Number:

Ethernet Address:

Description:

TCP/IP, WEB-site...


OK Cancel

Press OK, on this window.


# Application loader guide

## 9. Start loading the controller program:

- Click the Load Controller button.



If updating the EXOreal OS system is necessary, then this pop-up window appears:



# Application loader guide


The display in Regula Master changes to:



Then:




and finally:




# Application loader guide

Press OK, then the loading of the application program starts:




When the display looks as below in the display, then the OS loading is ready.






# Application loader guide


## 10. Afterwards load the Web application.




# Application loader guide



Click OK and wait for the Web-site to load:



When ready:



**For 3.0 and 3.1 versions**, which includes the HTML5 webserver Pascal Operate, if Pascal Operate has already run (with Google Chrome), then you must clear some browsing data on the computers:


- A. On the computer, open Google Chrome.
- B. At the top right, click More (three dots button).
- C. Click More tools Clear browsing data.
- D. At the top, choose a time range. Select All time is recommended.
- E. Check the boxes next to “Cookies and other site data” and “Cached images and files”. Other boxes should be left unchecked (leaving history-, login/password data etc. untouched).
- F. Click Clear data.
- G. Restart Google Chrome.

**For 1.1, 2.0 and 2.1 versions:**


After an up-/ or downgrade of Regula Master version, it is necessary to clear the Temporary files of Java on your PC to get the Web-site running properly in Internet Explorer.

# Application loader guide

Start the Java Control Panel (Configure Java) - **ONLY** for version 2.1 or older:



Click on Settings in the General tab.



Click on Delete Files.



Most of us spend the majority of our time indoors. Indoor climate is crucial to how we feel, how productive we are and if we stay healthy.

We at Lindab have therefore made it our most important objective to contribute to an indoor climate that improves people's lives. We do this by developing energy-efficient ventilation solutions and durable building products. We also aim to contribute to a better climate for our planet by working in a way that is sustainable for both people and the environment.

[Lindab](#) | For a better climate